

THE CARD MAKER

THE CARD MAKER ALLOWS YOU TO CREATE PERSONALIZED GREETING CARDS, INVITATIONS, ETC.,. WHEN YOU DO CARE TO TO SEND THE VERY BEST, SEND ONE YOU MADE YOURSELF!

THIS PROGRAMS FEATURES 3 STANDARD HEIGHT FONTS, THE SUPER SET MODE, THE DOUBLE HEIGHT MODE (FOR BOTH STANDARD AND SUPER SET), FRAME I AND FRAME II.

AS WITH FIRST EDITION AND THE BANNER PRINTER, THIS PROGRAM NEEDS A GRAPHIC DESIGN FILE IN MEMORY AT ALL TIMES. THE CARD SIZE WILL ALSO BE AFFECTED BY THE SIZE OF THE GRAPHIC FILE.

PROGRAM NAME	THE CARD MAKER
VERSION	1.0
WRITTEN BY	ERIC BOISVERT
FILE MEMORY	19200 BYTES
GRAPHIC DESIGNS	15300 BYTES
MAX PAGE WIDTH	255 (4080 DPL)
MIN PAGE WIDTH	30 (480 DPL)
MAXIMUM LINES	255
MINIMUM LINES	16


FILE THE FILE OPTION HAS A FEW NEW SUB-OPTIONS THAT SHOULD BE EXPLAINED... **CLEAR CARD** CLEARS THE WHOLE CARD WHILE **CLEAR PAGE** ONLY CLEARS THE CURRENT WORKING PAGE.

THE CARD IS DIVIDED IN 4 EQUAL QUARTERS, THAT'S 2 QUARTER PAGES ACROSS BY 2 QUARTER PAGES HIGH. YOU CAN SELECT WHICH QUARTER PAGES YOU WILL USE BY MOVING THE ARROW OVER THE RIGHT PAGE NUMBER (1. FRONT COVER, 2. INSIDE COVER, 3. INSIDE BACK, 4. BACK COVER) AND PRESSING SPACE (FIRE). AN ARROW WILL APPEAR TO LET YOU KNOW THAT THE PAGE IS SELECTED.

PAGE WIDTH IS THE WIDTH IN CHARACTERS OF EACH QUARTER PAGE. TO CALCULATE THE PAGE WIDTH, TAKE THE PRINTER WIDTH DIVIDED BY 16 (IE: 480 DPL / 16 = 30 CHARACTERS PER QUARTER PAGE, 576 DPL / 16 = 36, 960 DPL / 16 = 60).

PAGE LENGTH IS THE NUMBER OF LINES OF EACH QUARTER PAGE. FOR AN 8 1/2" X 11" PAGE, IT SHOULD BE 44 (88 / 2 QUARTER PAGES HIGH = 44 LINES).

IF **PAGE WIDTH** OR **PAGE LENGTH** IS CHANGED OR A NEW GRAPHIC DESIGN FILE IS LOADED, THE CARD IS CLEARED. (AFTER LOADING A NEW GRAPHIC FILE, YOU MAY HAVE TO RESET **PAGE WIDTH** AND **PAGE LENGTH**).


 THESE 4 OPTIONS SELECT THE CURRENT WORKING PAGE. IT ALSO HOMES THE CURSOR TO THE BEGINNING OF THE PAGE.

TEXT THIS OPTION IS IDENTICAL TO THE ONE IN FIRST EDITION WITH THE EXCEPTION OF TAB.

TIPS FOR THE CARD MAKER

- * AS WITH FIRST EDITION AND THE BANNER PRINTER, IF YOU LOAD A NEW FONT, ALL TEXT THAT WAS ALREADY WRITTEN WITH THE OLD FONT WILL BE REPLACED WITH THE NEW ONE.
- * MOST OF THE TIME, ONLY QUARTER PAGE 1 AND 3 ARE USED TO CREATE A CARD. HOWEVER, YOU MAY USE ALL 4 BUT YOU WILL HAVE TO MAKE SURE THE GRAPHIC DESIGN FILE IS NOT TOO LONG OR THE CARD WILL HAVE TO BE SMALLER.

HOW TO FOLD A CARD



A: FOLD BACKWARDS

B: FOLD SO THAT PAGE 1 IS ON TOP

C: END RESULT